AxTraxPro[™]

Access Control Management Software V28.0.4.0

Release Notes



1. General

These Release Notes cover the following products:

- AxTraxPro[™] Server
- AxTraxPro[™] Desktop Client
- AxTraxPro™ Web Client
- AxTraxPro™ Mobile Application

1.1. Product Overview

Rosslare AxTraxPro™ management software enables setting automated physical access control policy across facilities, perfect for today's most demanding users and organizations. The system can manage thousands of Rosslare networked access controllers and users, providing enhanced security with excellent system scalability and performance.

Integrated with video management systems and combing Rosslare state-of-the-art access control components including controllers, readers, credentials, and other peripherals, the complete ecosystem is optimal for almost any need.

2. Related Documentation

The following documents for this release have been uploaded and are available from the Rosslare web site.

- AxTraxPro Desktop Client V28.0.3.x User Guide.
- AxTraxPro Web Client V28.0.3.x User Guide.
- AxTraxPro Datasheet.
- AxTraxPro Brochure.
- · Hikvision MinMoe Setup Guide.
- AxTraxPro IDEMIA Bio On Card Integration Guide.
- AxTraxPro IDEMIA Face Recognition Terminal Integration Guide



AxTraxPro KONE Elevator Control Integration Guide.

3. Supported Hardware Products

AC-825IP Networked Control Panel & Expansions

- AC-825IP (Networked Control Panel built into ME-1515 Enclosure).
- AC-825IP-PCBA (Control Panel Only)
- R-805 (16 Relay Output Expansion for AC-825IP)
- S-805 (8 Sensor Input Expansion for AC-825IP).
- D-805 (4 Reader door Interface Expansion for AC-825IP).
- P-805 (16 Inputs, 8 Relay Output Expansion for AC-825IP).

AC-215IP/AC-225IP/ AC-425IP Networked Control Panels & Expansions

- AC-215, AC-215IP, AC-215-B/215IP-B.
- AC-225/225IP, AC-225-B/225IP-B with MD-D02, MD-I084 expansions.
- AC-425/425IP, AC-425-B/425IP-B with MD-D04, MD-I084 expansion.

Rosslare BI09000 Series Fingerprint Terminals

- AY-B9120BT: Outdoor networked optical fingerprint with 125 KHz (EM) RFID card reader.
- AY-B9150BT: Outdoor networked optical fingerprint with 13.56 MHz (MIFARE) RFID card reader.
- AY-B9250BT: Outdoor networked optical fingerprint with 13.56 MHz (MIFARE) RFID card reader + LCD + 4 touch buttons and camera.
- AY-B9350: Indoor networked optical fingerprint with Face recognition + EM (125 KHz) and MIFARE (13.56 MHz) card reader.
- DR-B9000: USB 2.0 fingerprint enrollment scanner and desktop reader.

4. Summary of Main Features

4.1. AxTraxPro Desktop Client

- AC-825IP supports SNMP
- Sub department support
- Mapping main Access group to a department.
- Integration with basIP intercom system was added, see Supported Integrated Products.
- Integration with IDEMIA VisionPass and VisionPass SP were added, see Supported Integrated Products.
- Supports MS-SQL 2022.

5. Resolved Issues

5.1. AxTraxPro Desktop Client

- #45389 Slow loading time when there are many users in the database.
- #45838 Users are not transferred if the photo file name is invalid.
- #46956 The AC-825IP's MAC address is not editable.

6. Known Issues

6.1. AxTraxPro Desktop Client

- Each user can only enroll a single face template. This means that only one model of face terminal can be used per site.
- In the SNMP manager, the response time for AC-825IP must be set to 3 seconds minimum.
- #34640 After an Automatic Operation AC link is activated with an AC-825IP with or without a D-805 expansion board, the opened output closes when a Manual Door Operation occurs.
- #37610 When the control panel is powered up during lockdown, lockdown is released and all doors are unlocked.
- #45241 The AC Link for Duress code does not work on AC-825.
- Some OSDP and OSDP SC outputs (LED & Buzzer and Events) do not work as expected.
- Some lockdown configurations do not work as expected.

6.2. AxTraxPro Web Client

• In some conditions, the user interface may not operate as expected.

6.3. General



AxTraxPro and AxTraxNG cannot be installed on the same computer.

- When BIO8000, BIO9000 and Hikvision biometric series devices are used at the same site, users must perform finger enrollment in the client for each BIO8000, BIO9000 and Hikvision device.
- The failure to enroll a fingerprint from BIO9000 devices while it is set to Live Fingerprint Detection.
- Downgrading AY-B91x0BT firmware from v3006-2 to v2_003_64 fails, but the terminal will still work with the previous version.
- Upgrading AY-B91x0BT firmware from v2_003_64 to v3006-2 fails. You can upgrade v2.x.x to a different v2.x.x version, and from v3xx to a different v3xx version.
- When migrating from AxTraxNG to AxTraxPro, all operators will be deleted except Administrator. It is highly recommended to document this data externally before the migration.



7. Supported Languages

7.1. Desktop Client

- Chinese, Simplified
- Dutch
- English
- French
- Greek
- Hebrew

- Portuguese
- Russian
- Slovenian
- Spanish
- Turkish

7.2. Web Client

- Chinese, Simplified
- English
- French
- Hebrew

- Polish
- Portuguese
- Spanish
- Turkish

8. Firmware Versions

| Software Version | Controller Model | Firmware Version | |
|----------------------|----------------------|------------------|--|
| | AC-825IP | AC825v05_00_01 | |
| | D805 | x805v04_05_02 | |
| | P805 | x805v04_05_02 | |
| | \$805 | x805v04_05_02 | |
| AxTraxPro V28.0.3.x | R805 | x805v04_05_02 | |
| AX 118XP10 V26.U.3.X | AC-425B | ac425v05_03_00 | |
| | AC-425A | ac425v05_03_00 | |
| | AC-225B | ac225v05_03_00 | |
| | AC-215B / AC-215IP-B | ac215Bv05_03_00 | |
| | AC-215A | ac215v04_08_24 | |



| Software Version | Terminal Model | Firmware Version | | |
|------------------|----------------------|------------------|--|--|
| | AY-B9120BT | 2_003_64 | | |
| | | 3006-2 | | |
| | AY-B9150BT | 2_003_64 | | |
| BIO9000 | | 3006-2 | | |
| | AY-B9250BT | 1023_36 | | |
| | AY-B9350BT | 1.56-011.15 | | |
| | DR-B9000 | | | |
| Software Version | Desktop Reader Model | Firmware Version | | |
| | DR-U955BT | DR-U995-V_01_06 | | |

9. Supported Integrated Products

9.1. Video

| Vendor Name | Product Type | Version | |
|-------------|--------------|-------------|--|
| Hikvision | SDK | 5.3.2.15 | |
| Dahua | SDK | 3.4.8.27787 | |

9.2. Biometric Devices

| Vendor Name | Product Category | Product Model | Latest Tested Firmware Version |
|-------------------------|---|-----------------|--------------------------------|
| | Value Series | DS-K1A340WX | 1.2.1_211022 |
| | | DS-K1T343MWX | 3.3.4_211022 |
| | | DS-K1T341AM | 3.2.30_220610 |
| | | DS-K1T341CMF | 3.3.8_220531 |
| Hikvision (Hikvision | | DS-K1T341AMF | 3.2.30_220610 |
| Verified) ¹ | Pro Series | DS-K1T671M | 3.2.30_220913 |
| | | DS-K1TA70MI-T | 3.2.35_220610 |
| | Ultra Series | DS-K1T671TM-3XF | 3.2.35_220610 |
| | Face Recognition Modules for Turnstile | DS-K5671-ZU | 3.2.30_220913 |
| | SIGMA Range (Bio On Card) | - | - |
| IDEMIA | VisionPass | - | - |
| | VisionPass SP | | |



9.3. License Plate Recognition (LPR)

| Vendor Name | Product Model | Tested Firmware Version | |
|-------------|---|-------------------------|--|
| Hikvision | DS-2CD7A26G0/P-IZHSWG (2.8-12mm) V5.6.10 build 200414 | | |
| | DS-2CD7A26G0/P-IZHSWG (8-32mm) | V5.6.10 build 200414 | |
| | iDS-2CD7A26G0/P-IZHSY | V5.5.130 build 210309 | |
| AVUTEC | X-Series | - | |

9.4. Elevator System

| Vendor Name | Supported API Version | |
|--------------------------|-----------------------------------|--|
| KONE Destination Control | KONE Connectivity Suite (API 500) | |

9.5. Intercom System

| w | an | 40 | or N | 10 | m | $\overline{}$ |
|----|----|----|-------|----|---|---------------|
| ·V | еп | ш | יו ונ | Vа | | |

basIP - LINK cloud server



10. Supported Microsoft Windows OS / Minimum Requirements

10.1. Software Requirements

- Windows 11 64-bit, Windows 10 64-bit, Windows Server 2016 and above
- .NET framework 4.8
- Visual C++ 2008 SP1 Redistributable Package (x86)
- .NET Core 5

10.2. Hardware Requirements

- Intel core i5, 2.4 GHz or equivalent
- 500 GB hard disk with a minimum of 8GB free space
- 8 GB RAM
- 10/100 Ethernet Port
- Mouse
- Keyboard
- Display

10.3. Supported SQL versions

- MS-SQL 2019
- MS-SQL 2022

All product names, logos, and brands are property of their respective owners.

DISCLAIMER: The data contained within Rosslare's materials or documentation is intended to provide only general information about products available for purchase from Rosslare and its associated companies ("Rosslare"). Reasonable efforts have been made to ensure the accuracy of this information. However, it might contain typographic errors, inaccuracies, or omissions that may relate to product descriptions, visual pictures, specifications, and other details. All technical specifications weights, measures and colors shown, are best approximations. Rosslare can not be held responsible and assumes no legal liability for the accuracy or completeness of the information provided. Rosslare reserves the right to change, delete, or otherwise modify the information, which is represented, at any time, without any prior notice.

© 2024 Rosslare All rights reserved.

For more information regarding support, visit https://support.rosslaresecurity.com.